Creating Realistic Lighting Effects for a Fireplace

Reference Number: **KB-01234** Last Modified: **June 28, 2023**

The information in this article applies to:



QUESTION

How can I make my fireplace appear to be glowing and casting light around my room?



ANSWER

Adjust fire materials to have an emissive value and then add additional lights to provide a realistic, glowing, fireplace effect.

To create a 'Glowing Flame' effect

1. **Open** the plan that contains a fire material that you'd like to modify.

- 2. Navigate **3D> Create Perspective View> Full Camera io** and and click and drag towards the fire material to create a camera view.
- 3. Next, select **3D> Adjust Materials> Adjust Material Definition** *(* and click on the flame material.

Note: If the flame material is behind a glass panel or other obstacle, you can click on the Delete Surfaces tool and then click on the glass panel to temporarily hide that component.

4. On the **P**ROPERTIES panel of the **Define Material** dialog that displays, increase the **Emissive** setting to your liking, then click **OK**.


Define Materia	I
Pattern Texture Properties Materials List	Material Name: Fireplace Fire Material Class: General Material Metallic Diffuse: Metallic Diffuse: Metallic Diffuse: Diffuse:

Emissive controls how bright a material appears independent of the lighting in the scene. It can be used to simulate surfaces that are glowing with their own light. Use the Emissive drop-down list or input your own value using the spin control arrows or text field. This setting is only available for General materials.

The flame should now appear to be glowing.

To create the lighting for the rest of the room

- 1. From a floor plan view, select **3D> Lighting> Add Lights**
- 2. Left-click and drag in front of the fireplace to draw a spot light facing away from the fireplace.



Note: If you have trouble selecting the light, try dragging a selection marquee encompassing the spot light. You can also navigate to 3D> Lighting> Adjust Lights, select the spot light that was created in the Adjust Lights dialog that appears, then click the Adjust button.

4. On the LOCATION panel of the **Light Specification** dialog that displays, specify the floor and height properties for the light.

In this example, 1 is specified as the Floor Number and the Absolute Elevation is set to 24".

5. On the LIGHT DATA panel, specify your desired properties for the spot light, then click **OK**.

In this example, the Color is set to orange, the Cut Off Angle is set to 180°, and the Drop Off Rate is set to 12.0.

fication												
Ligł	nt Sources											
Na	me	On	Sourc	ce Type	Intensity		Color	Used	In	Casts Shadows	Show Position	
Ad	ded Light		Spot	~	1200.0	÷		All Views	~			
												_
A	dd Light Copy l	light D	elete Lig	ht								
Ligł	nt Characteristics —											
	Source Type:	Spot	~									
	Intensity:	1200 Lur	mens	~ 1200	.0 ≑							
	Color:]								
	Tilt Angle:	0.0°										
•	Direction Angle:	270.0°										
	Cut Off Angle:	180.0°										
	Drop Off Rate:	12.0										
	Soft Shadows (CPU	Ray Tracin	ig) —									
	Light Diameter:	2"										
Offs	et											
	X Position:	0"										
	Y Position:	0"										
	Z Position:	0"										
Opt	ions											
	Used In: All View	WS	~	🗹 On in	Default Light	Set						
					Shadows							
				Show	Position in C	amera	View					
								ОК		Cancel	Hel	p

The room will now be lit by the spot light in front of the fireplace, and appear as though the light is coming from the fire.

Related Articles
Blending Colors with Materials (/support/article/KB-00004/blending-colors-with-
<u>materials.html)</u>
Changing the Transparency of a Material (/support/article/KB-00097/changing-the-
<u>transparency-of-a-material.html)</u>
Creating a Custom Fireplace and Chimney
<pre>(https://www.homedesignersoftware.com/support/article/KB-00744/creating-a-</pre>
<u>custom-fireplace-and-chimney.html)</u>



Privacy Policy (/company/privacy.html)